Kongsberg ACS control

Software release note



Software release note

Release 1.9.5 (APOS 4)/5.3.6 (APOS 5)

• Auto shutdown function for ACS500 implemented

Improvements

- The Exit button is moved to the Utility tab
- Added inactivity splash screen, when the screen goes blank, to avoid accidental selections in the menu
- Fixed generating ACS report
- The button for copying the log file was missing in versions from 1.8.0/5.2.0, it is now back

Release 1.9.0 (APOS 4)/5.3.0 (APOS 5)

• Support for more than one Arm and Disarm valve functions

Improvements

- Night palette issues are fixed
- Adding missing report entries when selecting replace SCU

Release 1.8.0(APOS 4)/5.2.0 (APOS 5)

• Replace SCU with spare unit implemented

Improvements

• Automatically setting topside TX power after changing between FSK and Cymbal

Release 1.7.0(APOS 4)/5.1.0 (APOS 5)

• Introduced version 5.1.0 of ACS control, which is the first version for APOS 5

Improvements

- Updated Auto shutdown GUI
- Reset all divided into Reset SCU1 and Reset SCU2